

Demo-Rack mobile IoT V1.0

BECKHOFF



Power Supply / Switches 24 V

BECKHOFF

Supply

24 V DC max. 4 A

S01


C6015 (24 V) on/off

Fuse F01 (4 A)

S02

I/O (24 V) on/off


Fuse F02 (4 A)





Switches S10 – S17

BECKHOFF



Switches
S10 – S17
↑latching / ↓ momentary

| Control Element | Input (Digital) | Terminal Position | Signal Type |
|------------------------|--------------------------|-------------------------------|-------------|
| S10 N/O contact | EL1859 - Input 1 - Pin 1 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| S11 N/O contact | EL1859 - Input 2 - Pin 2 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| S12 N/O contact | EL1859 - Input 3 - Pin 3 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| S13 N/O contact | EL1859 - Input 4 - Pin 4 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| S14 N/O contact | EL1859 - Input 5 - Pin 5 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| S15 N/O contact | EL1859 - Input 6 - Pin 6 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| S16 N/O contact | EL1859 - Input 7 - Pin 7 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| S17 N/O contact | EL1859 - Input 8 - Pin 8 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |

LEDs H10 – H17

BECKHOFF



LEDs
H10 - H17

| Control Element | Output (Digital) | Terminal Position | Signal Type |
|-----------------|----------------------------|-------------------------------|-------------|
| H10 | EL1859 - Output 1 - Pin 9 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| H11 | EL1859 - Output 2 - Pin 10 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| H12 | EL1859 - Output 3 - Pin 11 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| H13 | EL1859 - Output 4 - Pin 12 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| H14 | EL1859 - Output 5 - Pin 13 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| H15 | EL1859 - Output 6 - Pin 14 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| H16 | EL1859 - Output 7 - Pin 15 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |
| H17 | EL1859 - Output 8 - Pin 16 | -BC1(EK1100) -> -DC1 (EL1859) | BOOL |



Switches S20 – S27

BECKHOFF



Switches
S20 – S27
↑latching / ↓ momentary

| Control Element | Input (Digital) | Terminal Position | Signal Type |
|------------------------|--------------------------|-------------------------------|-------------|
| S20 N/O contact | EL1859 - Input 1 - Pin 1 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| S21 N/O contact | EL1859 - Input 2 - Pin 2 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| S22 N/O contact | EL1859 - Input 3 - Pin 3 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| S23 N/O contact | EL1859 - Input 4 - Pin 4 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| S24 N/O contact | EL1859 - Input 5 - Pin 5 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| S25 N/O contact | EL1859 - Input 6 - Pin 6 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| S26 N/O contact | EL1859 - Input 7 - Pin 7 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| S27 N/O contact | EL1859 - Input 8 - Pin 8 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |

LEDs H20 – H27

BECKHOFF



LEDs
H20 – H27

| Control Element | Output (Digital) | Terminal Position | Signal Type |
|-----------------|----------------------------|-------------------------------|-------------|
| H20 | EL1859 - Output 1 - Pin 9 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| H21 | EL1859 - Output 2 - Pin 10 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| H22 | EL1859 - Output 3 - Pin 11 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| H23 | EL1859 - Output 4 - Pin 12 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| H24 | EL1859 - Output 5 - Pin 13 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| H25 | EL1859 - Output 6 - Pin 14 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| H26 | EL1859 - Output 7 - Pin 15 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |
| H27 | EL1859 - Output 8 - Pin 16 | -BC1(EK1100) -> -DC2 (EL1859) | BOOL |

Potentiometer R10 - R11

BECKHOFF



Potentiometer
R10 - R11
(10V / 10k Ohm)

| Control Element | Input (Analog) | Terminal Position | Signal Type |
|-----------------|--------------------------|-------------------------------|-------------|
| R10 | EL3255 - Input 1 - Pin 2 | -BC1(EK1100) -> -AI1 (EL3255) | INT |
| R11 | EL3255 - Input 2 - Pin 5 | -BC1(EK1100) -> -AI1 (EL3255) | INT |

Handwheel / push button S18

BECKHOFF




Handwheel / Push Button S18
24 increments / rotation x 4-fold evaluation

| Control Element | Input (Digital) | Terminal Position | Signal Type |
|------------------------|----------------------------------|-------------------------------|-------------|
| S18 Handwheel | EL5151 – Input A / B - Pin 1 / 5 | -BC1(EK1100) -> -PM1 (EL5151) | UINT |
| S18 Push Button | EL5151 - Latch - Pin 8 | -BC1(EK1100) -> -PM1 (EL5151) | BOOL |

Heating


BECKHOFF




| Control Element | Input (Digital) | Terminal Position | Signal Type |
|----------------------------|---------------------------|-------------------------------|-------------|
| -E1 Heating 1 | EL2034 – Output 1 - Pin 1 | -BC1(EK1100) -> -D01 (EL2034) | BOOL |
| -E1 Heating 1 aktiv | EL1004 – Input 1 - Pin 1 | -BC1(EK1100) -> -DI1 (EL1004) | BOOL |
| -E2 Heating 2 | EL2034 – Output 2 - Pin 5 | -BC1(EK1100) -> -D02 (EL2034) | BOOL |
| -E2 Heating 2 aktiv | EL1004 – Input 2 - Pin 5 | -BC1(EK1100) -> -DI2 (EL1004) | BOOL |
| -H1 Led 1 | EL2034 – Output 3 - Pin 4 | -BC1(EK1100) -> -D03 (EL2034) | BOOL |
| -H2 Led 2 | EL2034 – Output 4 - Pin 8 | -BC1(EK1100) -> -D04 (EL2034) | BOOL |

Thermocouples

BECKHOFF




| Control Element | Input (Digital) | Terminal Position | Signal Type |
|--------------------------|-----------------------------|-------------------------------|-------------|
| -R1 Heating 1 | EL3318 – Input 1 - Pin 1/9 | -BC1(EK1100) -> -AI2 (EL3318) | INT |
| -R2 Heating 1 | EL3318 – Input 2 - Pin 2/10 | -BC1(EK1100) -> -AI2 (EL3318) | INT |
| -R3 Heat sink | EL3318 – Input 3 - Pin 3/11 | -BC1(EK1100) -> -AI2 (EL3318) | INT |
| -R4 Cover heating | EL3318 – Input 4 - Pin 4/12 | -BC1(EK1100) -> -AI2 (EL3318) | INT |
| -R5 Ambient | EL3318 – Input 5 - Pin 5/13 | -BC1(EK1100) -> -AI2 (EL3318) | INT |



| Control Element | Input (Digital) | Terminal Position | Signal Type |
|-----------------|-----------------------------------|-------------------------------|-------------|
| -M1 Fan | EL7332 – Motor Output 1 - Pin 1/5 | -BC1(EK1100) -> -PM2 (EL7332) | INT |

Power measurement

BECKHOFF



| Control Element | Input (Digital) | Terminal Position | Signal Type |
|----------------------|----------------------------|-------------------------------|-------------|
| -E1 Heating 1 | EL3443 – Voltage 1 - Pin 1 | -BC1(EK1100) -> -AI3 (EL3443) | BOOL |
| -E1 Heating 1 | EL3443 – Current 1 - Pin 5 | -BC1(EK1100) -> -AI3 (EL3443) | BOOL |
| -E2 Heating 2 | EL3443 – Voltage 2 - Pin 2 | -BC1(EK1100) -> -AI3 (EL3443) | BOOL |
| -E2 Heating 2 | EL3443 – Current 2 - Pin 6 | -BC1(EK1100) -> -AI3 (EL3443) | BOOL |
| -M1 Fan | EL3443 – Voltage 3 - Pin 3 | -BC1(EK1100) -> -AI3 (EL3443) | BOOL |
| -M1 Fan | EL3443 – Current 3 - Pin 7 | -BC1(EK1100) -> -AI3 (EL3443) | BOOL |



Example variables declaration

Global variables I/O

BECKHOFF

```
(* GVL00_IO *)
{attribute 'TcContextName' := 'PlcTask'}
VAR_GLOBAL

(* EL1859 digital inputs and outputs *)
{attribute 'OPC.UA.DA' := '1'}
bSwitchS10
{attribute 'OPC.UA.DA' := '1'}
bSwitchS11
{attribute 'OPC.UA.DA' := '1'}
bSwitchS12
{attribute 'OPC.UA.DA' := '1'}
bSwitchS13
{attribute 'OPC.UA.DA' := '1'}
bSwitchS14
{attribute 'OPC.UA.DA' := '1'}
bSwitchS15
{attribute 'OPC.UA.DA' := '1'}
bSwitchS16
{attribute 'OPC.UA.DA' := '1'}
bSwitchS17

{attribute 'OPC.UA.DA' := '1'}
bLedH10
{attribute 'OPC.UA.DA' := '1'}
bLedH11
{attribute 'OPC.UA.DA' := '1'}
bLedH12
{attribute 'OPC.UA.DA' := '1'}
bLedH13
{attribute 'OPC.UA.DA' := '1'}
bLedH14
{attribute 'OPC.UA.DA' := '1'}
bLedH15
{attribute 'OPC.UA.DA' := '1'}
bLedH16
{attribute 'OPC.UA.DA' := '1'}
bLedH17

AT%I* :BOOL; (* Switch S10 - heating 1 on/off *)
AT%I* :BOOL; (* Switch S11 - heating 2 on/off *)
AT%I* :BOOL; (* Switch S12 - fan on/off *)
AT%I* :BOOL; (* Switch S13 - blinker 1 on/off *)
AT%I* :BOOL; (* Switch S14 - blinker 2 on/off *)
AT%I* :BOOL; (* Switch S15 - clock signal 500ms on/off*)
AT%I* :BOOL; (* Switch S16 - clock signal 1s on/off*)
AT%I* :BOOL; (* Switch S17 - clock signal 2s on/off*)

AT%Q* :BOOL; (* LED H10 - heating 1 on *)
AT%Q* :BOOL; (* LED H11 - heating 2 on *)
AT%Q* :BOOL; (* LED H12 - fan 1 on *)
AT%Q* :BOOL; (* LED H13 - blinker 1 *)
AT%Q* :BOOL; (* LED H14 - blinker 2 *)
AT%Q* :BOOL; (* LED H15 - clock signal 500ms *)
AT%Q* :BOOL; (* LED H16 - clock signal 1s *)
AT%Q* :BOOL; (* LED H17 - clock signal 2s *)
```

Example variables declaration

Global variables I/O

BECKHOFF

```
(* EL1859 digital inputs/outputs *)
{attribute 'OPC.UA.DA' := '1'}
bSwitchS20
{attribute 'OPC.UA.DA' := '1'}
bSwitchS21
{attribute 'OPC.UA.DA' := '1'}
bSwitchS22
{attribute 'OPC.UA.DA' := '1'}
bSwitchS23
{attribute 'OPC.UA.DA' := '1'}
bSwitchS24
{attribute 'OPC.UA.DA' := '1'}
bSwitchS25
{attribute 'OPC.UA.DA' := '1'}
bSwitchS26
{attribute 'OPC.UA.DA' := '1'}
bSwitchS27

{attribute 'OPC.UA.DA' := '1'}
bLedH20
{attribute 'OPC.UA.DA' := '1'}
bLedH21
{attribute 'OPC.UA.DA' := '1'}
bLedH22
{attribute 'OPC.UA.DA' := '1'}
bLedH23
{attribute 'OPC.UA.DA' := '1'}
bLedH24
{attribute 'OPC.UA.DA' := '1'}
bLedH25
{attribute 'OPC.UA.DA' := '1'}
bLedH26
{attribute 'OPC.UA.DA' := '1'}
bLedH27

AT%I* :BOOL; (* Switch S20 - not in use *)
AT%I* :BOOL; (* Switch S21 - not in use *)
AT%I* :BOOL; (* Switch S22 - not in use *)
AT%I* :BOOL; (* Switch S23 - not in use *)
AT%I* :BOOL; (* Switch S24 - not in use *)
AT%I* :BOOL; (* Switch S25 - not in use *)
AT%I* :BOOL; (* Switch S26 - not in use *)
AT%I* :BOOL; (* Switch S27 - not in use *)

AT%Q* :BOOL; (* LED H20 - temperature heat sink >23.75C° *)
AT%Q* :BOOL; (* LED H21 - temperature heat sink >27.50C° *)
AT%Q* :BOOL; (* LED H22 - temperature heat sink >31,25C° *)
AT%Q* :BOOL; (* LED H23 - temperature heat sink >35.00C° *)
AT%Q* :BOOL; (* LED H24 - temperature heat sink >38.75C° *)
AT%Q* :BOOL; (* LED H25 - temperature heat sink >42.50C° *)
AT%Q* :BOOL; (* LED H26 - temperature heat sink >46.25C° *)
AT%Q* :BOOL; (* LED H27 - temperature heat sink >50.00C° *)
```

Example variables declaration

Global variables I/O

BECKHOFF

```
(* EL1004 digital inputs *)
{attribute 'OPC.UA.DA' := '1'}
bHeating1Aktiv
{attribute 'OPC.UA.DA' := '1'}
bHeating2Aktiv

(* EL2034 digital outputs *)
{attribute 'OPC.UA.DA' := '1'}
bHeating1
{attribute 'OPC.UA.DA' := '1'}
bHeating2
{attribute 'OPC.UA.DA' := '1'}
bHeating1Led
{attribute 'OPC.UA.DA' := '1'}
bHeating2Led

(* EL3255 0..10V analog inputs *)
{attribute 'OPC.UA.DA' := '1'}
nAnalogInR10
{attribute 'OPC.UA.DA' := '1'}
nAnalogInR11

(* EL5151 incremental encoder 24 increments/rotation * 4-fold evaluation -> 96 increments/rotation*)
{attribute 'OPC.UA.DA' := '1'}
nHandwheelCounter
{attribute 'OPC.UA.DA' := '1'}
bHandwheelSwitchS18
```

| | |
|--|---|
| | AT%I* :BOOL; (* Heating 1 aktiv *) |
| | AT%I* :BOOL; (* Heating 2 aktiv *) |
| | AT%Q* :BOOL; (* Heating 1 *) |
| | AT%Q* :BOOL; (* Heating 2 *) |
| | AT%Q* :BOOL; (* Heating 1 Led - flash slow (temperature > 40.0) – flash fast (temperature > 45.0) *) |
| | AT%Q* :BOOL; (* Heating 2 Led - flash slow (temperature > 40.0) – flash fast (temperature > 45.0) *) |
| | AT%I* :INT; (* Analog input R10 - fan velocity *) |
| | AT%I* :INT; (* Analog input R11 - blinker 1 flash speed *) |
| | AT%I* :UINT; (* handwheel counter *) |
| | AT%I* :BOOL; (* Switch S18 *) |

Example variables declaration

Global variables I/O

BECKHOFF

```
(* EL3318 8-channel thermocouple inputs *)
{attribute 'OPC.UA.DA' := '1'}
nTemperatureHeating1
{attribute 'OPC.UA.DA' := '1'}
nTemperatureHeating2
{attribute 'OPC.UA.DA' := '1'}
nTemperatureHeatSink
{attribute 'OPC.UA.DA' := '1'}
nTemperatureCoverHeating
{attribute 'OPC.UA.DA' := '1'}
nTemperatureAmbient

(* EL7332 2-channel DC motor output stage - fan *)
{attribute 'OPC.UA.DA' := '1'}
nFanStatus
{attribute 'OPC.UA.DA' := '1'}
nVeloFan
{attribute 'OPC.UA.DA' := '1'}
nFanContol

(* EL3443 3-phase power measurement terminal *)
{attribute 'OPC.UA.DA' := '1'}
fVoltageHeating1
{attribute 'OPC.UA.DA' := '1'}
fCurrentHeating1
{attribute 'OPC.UA.DA' := '1'}
fVoltageHeating2
{attribute 'OPC.UA.DA' := '1'}
fCurrentHeating2
{attribute 'OPC.UA.DA' := '1'}
fVoltageFan
{attribute 'OPC.UA.DA' := '1'}
fCurrentFan

END_VAR
(* End *)
```

| | | |
|--------------------------------|--------------|---|
| {attribute 'OPC.UA.DA' := '1'} | AT%I* :INT; | (* Temperature heating 1 *) |
| {attribute 'OPC.UA.DA' := '1'} | AT%I* :INT; | (* Temperature heating 2 *) |
| {attribute 'OPC.UA.DA' := '1'} | AT%I* :INT; | (* Temperature heat sink *) |
| {attribute 'OPC.UA.DA' := '1'} | AT%I* :INT; | (* Temperature cover heating *) |
| nTemperatureAmbient | AT%I* :INT; | (* Temperature ambient *) |
| {attribute 'OPC.UA.DA' := '1'} | AT%I* :UINT; | (* Fan status *) |
| {attribute 'OPC.UA.DA' := '1'} | AT%Q* :INT; | (* Fan velocity*) |
| nFanContol | AT%Q* :UINT; | (* Fan control *) |
| {attribute 'OPC.UA.DA' := '1'} | AT%I* :REAL; | (* Voltage heating 1 (V)*) |
| {attribute 'OPC.UA.DA' := '1'} | AT%I* :REAL; | (* Current heating 1 (A)*) |
| {attribute 'OPC.UA.DA' := '1'} | AT%I* :REAL; | (* Voltage heating 1 (V)*) |
| {attribute 'OPC.UA.DA' := '1'} | AT%I* :REAL; | (* Current heating 1 (A)*) |
| fVoltageFan | AT%I* :REAL; | (* Voltage fan 1 (V)*) |
| fCurrentFan | AT%I* :REAL; | (* Current fan 1 (power converter 1:32) (A*32) *) |

Beckhoff Automation GmbH & Co. KG

Head office
Hülshorstweg 20
33415 Verl
Germany

© Beckhoff Automation GmbH & Co. KG

All images are protected by copyright. Disclosure to and utilisation by third parties is not permitted.

Beckhoff®, TwinCAT®, EtherCAT®, Safety over EtherCAT®, TwinSAFE®, XFC® and XTS® are registered trademarks of and licensed by Beckhoff Automation GmbH. The use by third parties of other brand names or trademarks contained in this presentation may lead to an infringement of the rights of the respective trademark owner.

The information provided in this presentation only contains general descriptions or performance characteristics that may not necessarily apply to specific applications or may change during further product development. The required performance characteristics are only binding if they are explicitly agreed on completion of a contract.